



Adventure International



TO LOAD ADVENTURE ON YOUR APPLE 2/APPLE 2 PLUS

1. You must have 24 K or more memory. Apple Adventure does not support any lower case boards.
2. If you have a Disk on your system, boot it up into Applesoft.
3. If you are in Applesoft, do a call -151 to get into the system monitor, or optionally hit reset.
4. An* with a blinking cursor should now be showing to indicate you are in the system monitor.
5. Put Adventure tape into your recorder.
6. Rewind tape, there are 2 copies of the Adventure on both sides of the tape!
7. Remove the earplug from the Cassette Recorder.
8. Hit play on recorder.
9. When first tone is heard, hit stop on the recorder immediately.
10. *Type: 800.5777R on your Apple. *DO NOT HIT RETURN YET THOUGH!*
11. Hit play on your tape recorder.
12. Immediately hit return on your Apple. The tape will read for about 2 minutes.
13. If you want to save Adventure on your Disk, do the following now:
Type: [CTRL-D] BSAVE ADVENTURE, A\$800, L\$4F70, to later run it type BRUN
ADVENTURE FROM APPLESOFT.
14. To start Adventure, Type: 800G.
15. Adventure will start by asking if you wish to restore a previously saved game. If you had done a "save game" while playing ADVENTURE you would type YES, else just type NO! To restore a saved game from tape after typing "YES".
 - A. Remove earphone plug from recorder.
 - B. Rewind your saved tape.
 - C. Hit play on recorder.
 - D. When first tone is heard, hit stop on recorder.
 - E. Replace earphone plug.
 - F. The saved tape is now ready, you should see on the screen. Ready saved tape. Hit enter.
 - G. Hit play on the recorder.
 - H. Hit enter on your Apple immediately.
16. While playing Adventure - always look at the top of the screen to see where you are and what's currently visibly!
17. How to do a save game:
 - A. While playing Adventure type: Save Game.
 - B. It will ask Disk or Tape?
 - C. If you are saving it to tape reply - Tape.
 - D. It will respond ready saved tape, hit enter.
 - E. Put a blank tape in your recorder.
 - F. Rewind it and be sure the Cassette lead is plugged into the mike input.
 - G. Hit play and recorder on your recorder and wait till you are past the leader.
 - H. Hit enter.
18. If you should accidentally hit reset while playing Adventure:
 1. If you have firmware restart card type: CALL-151 to enter the monitor.
 2. Type: CTRL-Y and hit return.
 3. Type: LOOK
 4. Type: LOOK
 5. You are now back in Adventure!